



MXU 5.13 and OmniPC™ 5.13 Software

April 25, 2023

Version compatibility

MXU & OmniPC Software	5.13.0
System Update	1.8.0.2
Probe/Wedge Update	1.0.10.4
.nde Open File Format	3.1.0

X3 Remote Collaboration Services (X3 RCS)

* After May 6, 2023, versions 5.12.1 and lower will no longer support X3 RCS. Update to the 5.13.0 version to keep using this app. *

Added

- Compatibility with the new HydroFORM™ scanner
 - ScanDeck™ configuration under the Edit Encoders menu
 - 18 options under Probes & Wedges
- Merged B-scan display (patent pending *US20210096246A1*)
- External file saving direct to USB and SD card
- Projection Focusing
 - For linear probes in COD
 - For dual PA probes in AOD and COD
- True Depth Focusing for dual PA probes in AOD and COD
- Focal points displayed for COD
- Alarms and outputs (UT and PA)
- New Multiple A-B-S (PA) and Single B-S-A layouts

Improvements and bug fixes

- Improved *ONDT_Corrosion_3.pal* contrast when encoder counts are missing
- Maximized layout ratio for multigroup PA & TOFD (A-B-C PAUT) TOFD display
- Multiple bug fixes
- .nde open file improvements